

NOXAlert

Popup App

User manual

Version	Change	Done by
1.0	First version	Robert Banasiak
1.1	Minor corrections	Jasper Johansen
1.2	Added image example	Robert Banasiak
1.3	Multi-language and Text filter added	Jasper Johansen

The NOXAlert application is used to inform users about new alarms in the form of pop-up windows.

- Start the programme by double-clicking NOXAlert.exe.
- If this is your first time using NOXAlert you must fill out the System Setup.
- Type ip address, user code and select minimum one alarm type.
- Then press Save to save the settings.
- Restart the application.

System Setup

NOX System

IP Address / Hostname: 192.168.1.146

Security

SL3 SL4

Login

User code: ***

Alarmtype

Loop the sound alert

DK	EN	SE	Text
<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>


ARAS SECURITY
www.aras.dk

NOXAlert will automatically connect to the NOX central unit and minimize the window to the system tray.

A pop-up alert will appear as the top window until you click OK.

There will be played a single sound upon alarm, check off at "Loop the sound alert" to repeat the sound the alarm until you click OK.

You can set the display of special actions using the text filter function. For example, you can view all actions performed by "User Guest 10" by typing this in the text box.




The screenshot shows the ARAS System Setup dialog box. The window title is "System Setup" with the ARAS logo. The dialog is divided into several sections:

- NOX System:** Contains a text box for "IP Address / Hostname" with the value "192.168.1.146".
- Security:** Contains two radio buttons, "SL3" (selected) and "SL4".
- Login:** Contains a text box for "User code" with three asterisks "***".
- Alarmtype:** Contains a tabbed interface with tabs "DK", "EN", "SE", and "Text". The "Text" tab is selected and highlighted with a red box. Below the tabs is a "Text filter:" section with a text box containing "User Guest 10", also highlighted with a red box.

On the right side of the dialog, there are two buttons: "Save" and "Cancel". Below the "Text filter" section, there is a checked checkbox labeled "Loop the sound alert". At the bottom right, the ARAS Security logo and the website "www.aras.dk" are displayed.

You can always open the popup window again by tapping the Aras icon:



Example of attack alarm in the popup window:



Example of display of Alarm using text filter:

